Sew Much to Do! Supply List

To make this 36" x 32" wallhanging, you will need:

Cream Print (background) – 1 yard (This will be more than enough.)

Black Print (sewing machine/binding) $-1 \frac{1}{4}$ yards You need $\frac{1}{4}$ yard for the machine and 1 yard for the binding.

Coordinated Plaid or Floral (Outer Border) – ½ yard (Again, this will be more than enough)

Brown Print (tops and bottoms of spools / Mason jar lid) - 3/8 yard

Assorted Prints (spool thread) – You need a total of ¼ yard. See cutting instructions for specific cuts.

White Print (Mason jar) – Fat ¹/₄ Red Print – 4" x 4" piece Black Solid – 3" x 3" piece Yellow Solid – 5" x 2" piece

The following items you will need to finish the quilt. You most likely won't need them class:

- ✓ Lightweight fusible webbing (such as Heat and Bond)
- ✓ Assortment of buttons
- ✓ Embroidery floss
- ✓ Batting
- ✓ Backing

Sew Much to Do!

Cutting Directions

Finished size - 36" x 32"

Sewing Machine Block (18 1/2" x 14 1/2" unfinished) From black (machine) fabric cut: From cream (background) fabric cut: 2 - 13 3/8" x 5" 1 - 14 1/2" x 2 3/4"

 $1 - 4 \frac{1}{2}$ " x 5"

1 - 11" x 2 $\frac{3}{4}$ " $1 - 2\frac{1}{4}$ " x $2\frac{3}{4}$ "

2-1 1/8" x 2 3/4"

1-7½" x 5" $1 - 1\frac{3}{4}$ " x $1\frac{1}{4}$ "

1-13/4" x 10" 1-11/4" x 1 1/8"

Spool Border (18-4 1/2" x 4 1/2" unfinished) From assorted spool's thread fabrics cut: 18 - 2 1/2" x 2 1/2"

From cream (background) fabric cut: 36 - 1 1/2" x 2 1/2" 36 - 2" x 2" From brown spool fabric cut:

36 - 1 1/2" x 2 1/2" 36 - 2" x 2"

Corner Notions Tomato Pin Cushion

4" x 4" - red print fabric 4 1/2" x 4 1/2" background fabric Rotary Cutter 5" x 2" yellow print fabric

3" x 3" black solid fabric 4 1/2" x 4 1/2" background Button Jar $1 - 4 \frac{1}{2}$ " x 4 $\frac{1}{2}$ " white print

 $1 - 4 \frac{1}{2}$ " x 2 $\frac{1}{4}$ " white print

 $1 - 4 \frac{1}{2}$ " x 1" white print 1 - 1 3/4" x 3 1/2" brown print (lid)

2 - 1" x 1 3/4" background 2 - 1" x 1" background 1 - 4 1/2" x 11/4" background 2-2 1/4" x 2 3/4"

1-13/4" x 3 1/2" 1 - 1 1/8" x 2"

From spool (on the machine) fabric, cut $1 - 2\frac{1}{4}$ " x $2\frac{3}{4}$ "

Borders Length cuts are approximate From background fabric cut:

2-1½" x 18" $2 - 1 \frac{1}{2}$ " x 30" 2-1½" x 28" From Outer Border Fabric cut:

2-11/2" x 20"

2-3½" x 32" 2 - 3 1/2" x 34"

Sew Much to Do!

Directions

Finished Size: 33 1/2" x 37 1/2"




Making the Machine Block


- 1. Assemble sewing machine block (see hand-printed directions in back)
- 2. Sew a $1\frac{1}{2}$ " x 20" strip to each side of the machine block. Trim ends and press towards strip.
- 3. Sew a 1 ½" x 18" strip to the top and bottom of the machine block. Trim ends and press towards strip.
- 4. Make a needle on the machine using a satin stitch and black thread (either by hand or by machine).


Making the Spools


 On the wrong side of the cream 2" squares, draw a diagonal line. (Figure 1)



- 2. Place a cream square on top of a brown square right sides together and sew 1/4" from each side of the drawn line. (Figure 2)
 - Figure 2 Sewing line
- Cut apart on marked line and press open to make pieced squares. Make 72.
- 4. Using chain-piecing and following the diagram below, make 18 spools from your assortment of 2 ½" x 2 ½" spool fabrics.









Make 18 total

Making the Mason Jar Block


- One the wrong side of two 1" x 1" cream squares, draw a diagonal line. Place the squares on either end of the white 1" x 4 ½" rectangle. (Figure 3)
- 2. Sew on the drawn line. Cut excess and press open.



3. Assemble Jar Block as shown in Figure 4.




- 1. Finger press cream 4 ½" squares in half twice diagonally; use the folds as placement lines.
- 2. Following the lightweight fusible webbing directions and the templates below, cut and place the template fabrics in alphabetical order onto the cream squares. Applique in place.
- 3. Using black floss or thread, machine or hand sew around shapes with the buttonhole stitch. Backstitch details on Pincushion Block.



Assembling the Quilt Top

(Refer to the picture below as you follow these directions.)

- 1. To make the top and bottom pieced borders, arrange, stitch, and press 2 rows of 4 Spool Blocks each. Stitch to the top and bottom of the quilt. Press
- To make side pieced borders, arrange and stitch 1 vertical row using 6 Spool Blocks and a Pincushion Block on top. Arrange another vertical row using 4 Spool Blocks and a Rotary Cutter Block on top and the Mason Jar Block on the bottom. Stitch to the sides of quilt. Press.
- 3. Sew a cream 1 ½" x 30" strip to each side of quilt. Trim ends and press.
- 4. Sew a cream 1 1/2" x 28" strip to the top and bottom of quilt. Trim ends and press.
- 5. Sew a 3 ½" x 32" border strip to the each side of your quilt. Trim ends and press.
- 6. Sew a 3 ½" x 34" border strip to the top and bottom of your quilt. Trim ends and press.



- Layer, baste, and quilt as desired. Add finishing touches such as a black button in the middle of the rotary cutter and buttons in the Mason Jar.
- 8. Bind with the remaining black Sewing Machine Block fabric.

Sewing Machine Block (1412"x 1812") - Machine 1- cream D-Spool fabric 214 + 23)4 118"x2" Section a) 11/8" + 23/4" 118" × 114" a) Draw a diagonal line on 6) Place on right side corner of 5"x71/2" thewrong side of the black rectangle. Sew on drawn line. 23/4" × 23/4" square +rim Press open. (1) 41/2" > 5" Section Sections 2/3 2114"x 214+ 23/4" × 11" 23/4 = Spool fabric Section 114 + 13/4 13/4 × 10 13/4× 31/2


Section 3

sewing

Putting it all together:

1) Sew a 133/8" x 5 black rectangle to either side of Section 1. Press

a) Then sew Section 3 to the right side of Unit 1
Press.





Section 3

Unit 1

3) Sew Section 2 to the top of finished Unit 1. Press.

Then Sew 141/2" x 23/4" strip to the top of that Unit. Press





Finished Block